


# Cài đặt chứng chỉ SSL - Barracuda SSL VPN

admin Sun, Apr 14, 2019 [Chứng Chỉ Số SSL Certificates](#) 0 1847

1. Vào Barracuda SSL VPN. Chọn Tab BASIC > Chọn tab **SSL Certificate**.
2. Ở tab **SSL Certificate Configuration**, chọn **Trusted (Signed by a trusted CA)** trong danh mục **Certificate Type**.
3. Bên dưới khung **Trusted (Signed by a trusted CA)** chọn **Browse** ? Add File:.
4. Trong nút chia sẻ *Root.crt* và chọn **Upload**
5. Bịt s?nh?n dc thông báo **File Uploaded** khi th?c hi?n thành công



SSL VPN

BASIC ADVANCED

Status IP Configuration Administration SSL Certificate Help Search

File Uploaded

SSL Certificate Configuration

Certificate Type: Trusted (Signed by a trusted CA)    Select **Private** for the certificate type if you do not wish to purchase a certificate signed by a trusted Certificate Authority (CA) for your Barracuda SSL VPN.

Trusted (Signed by a trusted CA)

Certificate Signing Request (CSR):    If you need to obtain a **Trusted Certificate**. Enter your CSR data, then download the CSR to submit to a Certificate Authority (CA).

Add File:   Upload an SSL certificate, chain, key or archive in PEM, PKCS12, or various other formats. Once uploaded completely, click on the Use button to start using the uploaded certificate.

Cleanup:

Uploaded files	Uploaded Date	Status	Delete
Root.crt	2015-11-18 10:05:23	Valid file	<input type="button" value="Delete"/>

Synchronize SSL Certificate

Synchronizes the trusted SSL certificate used for the administrative (appliance) interface to that of the user (SSL VPN) interface.

## 6. Làm t??ng t? v?i *Intermediate.crt* và *SSLcert.crt*

SSL VPN

BASIC ADVANCED

Status IP Configuration Administration SSL Certificate Help Search

File Uploaded

SSL Certificate Configuration Save Changes Help

Certificate Type: Trusted (Signed by a trusted CA) Select **Private** for the certificate type if you do not wish to purchase a certificate signed by a trusted Certificate Authority (CA) for your Barracuda SSL VPN.

Trusted (Signed by a trusted CA) Save Changes Help

Certificate Signing Request (CSR): Edit Data Download CSR Download Key

If you need to obtain a Trusted Certificate: Enter your CSR data, then download the CSR to submit to a Certificate Authority (CA).

Add File:    Upload an SSL certificate, chain, key or archive in PEM, PKCS12, or various other formats. Once uploaded completely, click on the Use button to start using the uploaded certificate.

Cleanup: Clean All Unused Files

Uploaded files	Uploaded Date	Status	Delete
IntermediateCA.crt	2015-11-18 10:05:23	Valid file	<input type="button" value="Delete"/>

Synchronize SSL Certificate Help

Synchronize Synchronizes the trusted SSL certificate used for the administrative (appliance) interface to that of the user (SSL VPN) interface.

7. Sau khi upload 3 file thành công, ch?n vào **Use**.

SSL VPN Log Off English 

Search...

**BASIC ADVANCED**

**Status IP Configuration Administration SSL Certificate Help Search**

**File Uploaded**

**SSL Certificate Configuration** Save Changes Help

Certificate Type: **Trusted (Signed by a trusted CA)** Select **Private** for the certificate type if you do not wish to purchase a certificate signed by a trusted Certificate Authority (CA) for your Barracuda SSL VPN.

**Trusted (Signed by a trusted CA)** Save Changes Help

Certificate Signing Request (CSR): **Edit Data** **Download CSR** **Download Key** If you need to obtain a **Trusted Certificate**: Enter your CSR data, then download the CSR to submit to a Certificate Authority (CA).

Add File: **Browse...** Upload an SSL certificate, chain, key or archive in PEM, PKCS12, or various other formats. Once uploaded completely, click on the **Use** button to start using the uploaded certificate.

**Upload**

Cleanup: **Clean All Unused Files**

Uploaded files	Uploaded Date	Status	Delete
CN=www.yourdomain.com	2015-11-18 10:05:23	<b>OK</b>	<b>Use</b>

**Synchronize SSL Certificate** Help

**Synchronize** Synchronizes the trusted SSL certificate used for the administrative (appliance) interface to that of the user (SSL VPN) interface.

## 8. Cúi cung bñ hñy chñn **Synchronize**

**Synchronize SSL Certificate** Help

**Synchronize** Synchronizes the trusted SSL certificate used for the administrative (appliance) interface to that of the user (SSL VPN) interface.

Online URL: <https://huongdan.maxserver.com/article-38.html>